

# A Crash Course on SimpleCV

Katherine Scott

SightMachine

*[kat@sightmachine.com](mailto:kat@sightmachine.com) [anthony@sightmachine.com](mailto:anthony@sightmachine.com)*

March 3, 2013

# Overview

# Get Started!

There are a lot of dependencies for SimpleCV and it is a bit tough for beginners. We've brought disks that are ready to go!

- ▶ Windows / Linux
  - ▶ Boot from USB drive.
  - ▶ Alternatively install VirtualBox and the image.
  - ▶ <https://www.virtualbox.org/>
- ▶ Macs
  - ▶ Newer macs are persnikety about booting from a USB drive.
  - ▶ Install virtual box and the ISO and go to town.
- ▶ When you get home install from SuperPack or preferably source libs.
  - ▶ take awhile and is not a perfect science.
  - ▶ <https://github.com/ingenuitas/SimpleCV>
  - ▶ If you want to contribute this is a great place to start.

# About the tutorial

- ▶ It will be a lot of live coding. I'll lead, you follow along.
- ▶ If you have a question feel free to interrupt.
- ▶ If you are having an issue raise a flag. Anthony will help you.

# What Makes Up SimpleCV?



# SimpleCV $\neq$ OpenCV



- ▶ OpenCV is really busy, we help by wrapping python.
- ▶ We add lots of other fun stuff (OCR, Barcodes, etc.)
- ▶ We are not competing, we are complementing.
- ▶ Purposes are different. Python is great for prototyping. C++ great for embedded.

# Core Dependencies

- ▶ OpenCV Python Bindings
- ▶ Numpy
- ▶ SciPy
- ▶ SciKits Learn and Orange
- ▶ PyGame (this is going away)
- ▶ Python Imaging Library (PIL)
- ▶ ipython
- ▶ PIL (Python Imaging Library)

## Optional Dependencies


- ▶ Barcodes- Zebra Crossing ZXing
- ▶ Optical Character Recognition (OCR) - Tesseract
- ▶ Beautiful Soup
- ▶ Kinect Support - freenect
- ▶ Unit Tests - nose
- ▶ Web Stuff - flask / CherryPy
- ▶ Arduino - pyfirmata
- ▶ Many Many Many more.



# This is why we put everything in a superpack / virtual box / bootable drive

- ▶ Just get to the core library functions.
- ▶ We encourage you to install the full library when you get home.
- ▶ Help is available if you need it.

## Getting Help after the tutorial.



- ▶ Primary Source: <http://help.simplecv.org/questions/>
- ▶ Documentation <http://www.simplecv.org/docs/>
- ▶ Tweet at us: @Simple\_CV
- ▶ Another Good Resource:  
<http://www.reddit.com/r/ComputerVision>

## On the Printed Page




Figure: Two books about using Python for Computer Vision

## So why are we doing this?

- ▶ We are really nice people who believe in Python and Open Source.
- ▶ We are trying to disrupt industrial quality control systems.



# Early Prototypes




Figure: Early Customer - Industrial Fastener Morphology and Metallurgy

# Early Prototypes





Figure: Early Customer - Aquaponics Research Facility

# How do I SimpleCV?



# Where do I write my code?

So how do I SimpleCV?

- ▶ In a python file, just like any other library.
- ▶ In a command line REPL like iPython.
- ▶ In the browser using iPython Notebooks (we'll use this today).

We really like iPython. It is kinda like using Matlab without the \$ 5000 per seat license cost.



## How does fit into a work flow?

At SightMachine we roughly use these three tools for different parts of our workflow.

Tool	Uses
iPython REPL	Prototypes, Sanity Checks, Etc
iPython Web Notebook	Testing and Development
Python Files	Deployment Code

Table: SimpleCV Workflow


# SimpleCV Hello World as a Script

## Example (HelloWorld.py)

```
1  from SimpleCV import Image, Display, Color, Camera
2  cam = Camera(0) #Get the first camera
3  disp = Display((640,480)) # Create a 640x480 Display
4  while( disp.isNotDone() ):
5      img = cam.getImage() # get an image
6      # write text at 40,40 font_size 60pts, color is red
7      img.drawText("Hello World!",40,40,
8                  fontsize=60,color=Color.RED )
9      img.save(disp) # show it
10
```

# How do I run Hello World?

- ▶ Run the py file with *python HelloWorld.py* in the command.
- ▶ Close it by pressing *esc* or *ctrl – c*



# The SimpleCV Shell - Custom iPython REPL

Sometimes you just want to test an idea without writing a full script. For this reason we created the SimpleCV shell, which is a custom ipython instance. The SimpleCV shell will allow you to:

- ▶ Test your ideas in a REPL similar to Matlab.
- ▶ Access the SimpleCV documentation.
- ▶ Import modules that you are working with to test.
- ▶ Run through an interactive tutorial.

# Starting the SimpleCV Shell

In OSX and Linux just type *simplecv* at the command line. On Windows you just click on the SimpleCV icon.

## Example (Shell Basics)

```
+-----+
SimpleCV 1.3.0 [interactive shell] - http://simplecv.org
+-----+

Commands:
"exit()" or press "Ctrl+ D" to exit the shell
"clear" to clear the shell screen
"tutorial" to begin the SimpleCV interactive tutorial
"example" gives a list of examples you can run
"forums" will launch a web browser for the help forums
"walkthrough" will launch a web browser with a walkthrough

Usage:
dot complete works to show library
for example: Image().save("/tmp/test.jpg") will dot complete
just by touching TAB after typing Image().

Documentation:
help(Image), ? Image, Image ?, or Image() ? all do the same
"docs" will launch webbrowser showing documentation
```

# SimpleCV Shell Like a Boss



- ▶ Putting a `?` in front of a class or method will give you documentation. The `/` key will let you search.
- ▶ iPython has tab completion for methods.
- ▶ Up arrow will give you previous commands.
- ▶ `%paste` will let you paste formatted code.
- ▶ Other cool stuff can be found by googling iPython magic commands.


# Let's repeat Hello World in SimpleCV Shell

## Example (In the SimpleCV shell)

```
SimpleCV:1> cam = Camera()
SimpleCV:2> disp = Display((640,480))
SimpleCV:3> while disp.isNotDone():
...:     img = cam.getImage().edges()
...:     img.drawText("Hello World!",40,40,fontsize=60)
...:     img.save(disp)
...:
SimpleCV:4> exit
```

- ▶ Just push return after each line.
- ▶ iPython will do tabbing in the while loop.
- ▶ *esc* to quit or *ctrl* – *c*.
- ▶ type “exit” to quit.


# Yes, it really is that simple.



```
pygame window
Terminal
libusb: 3.507961 debug [sysfs_scan_device] scan 2-1.1.1
libusb: 3.508072 debug [sysfs_scan_device] bus=2 dev=9
libusb: 3.508089 debug [enumerate_device] busnum 2 devaddr 9 session_id 521
libusb: 3.508104 debug [enumerate_device] allocating new device for 2/9 (session_id 521)
libusb: 3.508193 debug [sysfs_scan_device] scan 2-1.1.2
libusb: 3.508302 debug [sysfs_scan_device] bus=2 dev=10
libusb: 3.508319 debug [enumerate_device] busnum 2 devaddr 10 session_id 522
libusb: 3.508334 debug [enumerate_device] allocating new device for 2/10 (session_id 522)
libusb: 3.508421 debug [discovered_devs_append] need to increase capacity
libusb: 3.508441 debug [sysfs_scan_device] scan 2-1.1.3
libusb: 3.508559 debug [sysfs_scan_device] bus=2 dev=11
libusb: 3.508577 debug [enumerate_device] busnum 2 devaddr 11 session_id 523
libusb: 3.508592 debug [enumerate_device] allocating new device for 2/11 (session_id 523)
libusb: 3.508744 debug [libusb_get_device_descriptor]
libusb: 3.508783 debug [libusb_get_device_descriptor]
libusb: 3.508813 debug [libusb_get_device_descriptor]
libusb: 3.508844 debug [libusb_get_device_descriptor]
libusb: 3.508874 debug [libusb_get_device_descriptor]
libusb: 3.508905 debug [libusb_get_device_descriptor]
libusb: 3.508937 debug [libusb_get_device_descriptor]
libusb: 3.508967 debug [libusb_get_device_descriptor]
libusb: 3.508999 debug [libusb_get_device_descriptor]
libusb: 3.509030 debug [libusb_get_device_descriptor]
VIDIOC_QUERYMENU: Invalid argument
VIDIOC_QUERYMENU: Invalid argument
VIDIOC_QUERYMENU: Invalid argument
VIDIOC_QUERYMENU: Invalid argument
VIDIOC_QUERYMENU: Invalid argument
VIDIOC_QUERYMENU: Invalid argument
VIDIOC_QUERYMENU: Invalid argument
SimpleCV:2> disp = Display((640,480))
SimpleCV:3> while disp.isNotDone():
...:     img = cam.getImage().edges()
...:     img.drawText("Hello World!", 40,40,fontsize=60)
...:     img.save(disp)
...:
```




# Why use iPython Web Notebooks



[online diagramming & design]  createely.com

- ▶ Web notebooks give you the best features of an IDE and a REPL.

# How do I use the notebook?



- ▶ From the shell just type *simplecv notebook -- pylab inline*.
- ▶ The *--pylab inline* is optional but it pulls in matplotlib which is handy.
- ▶ You will get to a dashboard to create a new notebook.
- ▶ By default notebooks are in the path where you start ipython.

# How do I use the notebook?

```

Type:      classobj
String Form: SimpleCV.ImageClass.Image
File:      /home/kscottz/SimpleCV/SimpleCV/ImageClass.py
Docstring:
**SUMMARY**

The Image class is the heart of SimpleCV and allows you to convert to and
from a number of source types with ease. It also has intelligent buffer
management, so that modified copies of the Image required for algorithms
such as edge detection, etc can be cached and reused when appropriate.

Image are converted into 8-bit, 3-channel images in RGB colorspace. It will
automatically handle conversion from other representations into this
standard format. If dimensions are passed, an empty Image is created.

**EXAMPLE**

>>> i = Image("/path/to/image.png")
>>> i = Camera().getImage()
  
```

- ▶ Everything we mentioned about the SimpleCV shell still holds.
- ▶ Magic commands, inline documentation, etc. still work.
- ▶ *enter* starts a new line.
- ▶ *ctrl – enter* executes a line.

# Caveats about iPython Web Notebooks



- ▶ iPython Web Notebooks are still version 0.1.4
- ▶ **There is no auto-save. Get in the *ctrl – s* save habit.**
- ▶ If you edit a module you import you must restart the core.
- ▶ Minimal editing support. No find/replace.
- ▶ The core can sometimes crash on large images.
- ▶ The notebooks hold on to data by default. This can fill up your version control system fast. Try the download as python command from the gui.

# Image Loading Basics II

- ▶ You can get the image file name using *img.filename*
- ▶ Images can also come from appropriately shaped numpy arrays.
- ▶ PIL and OpenCV images can also be passed into the image.
- ▶ Can also take a URL to an image.
- ▶ The `img.getEXIFData()` command can show jpg EXIF data.

# Saving an Image

- ▶ The `img.save()` command is used to save images.
- ▶ You can save as just about any format, PNG, JPG, WebP, etc.
- ▶ Calling save with no parameters saves it to temp directory.
- ▶ Using the params flag you can set compression, e.g. set compression quality.

# Using a USB Camera

- ▶ Most usb cameras use the **Camera** class.
- ▶ The camera class takes a camera index, *usually* this is the order cameras are plugged into the computer.
- ▶ The camera also has properties that you can get and set, or use a propmap dictionary to set.
- ▶ *Support for camera properties is vendor specific and spotty at best.*
- ▶ Cameras also have a *threaded* parameter. Set this to false to run multiple cameras.

- ▶ `Camera.getImage()` will return the current image.
- ▶ `Camera.getAllProperties()` will return the cameras properties.
- ▶ `Camera.getProperty()` and `Camera.setProperty()` may let you set properties. *This is highly vendor dependent and usually poorly documented.*



- ▶ `Camera.getImage()` will return the current image.
- ▶ `Camera.getAllProperties()` will return the cameras properties.
- ▶ `Camera.getProperty()` and `Camera.setProperty()` may let you set properties. *This is highly vendor dependent and usually poorly documented.*

- ▶ `Camera.getImage()` will return the current image.
- ▶ `Camera.getAllProperties()` will return the cameras properties.
- ▶ `Camera.getProperty()` and `Camera.setProperty()` may let you set properties. *This is highly vendor dependent and usually poorly documented.*

## Briefly: Other Cameras

- ▶ Kinect - Depth Camera
  - ▶ Uses freenect drivers, not the OpneNI drivers.
  - ▶ `Kinect.getImage` and `Kinect.getDepth`
  - ▶ Note that these aren't well calibrated together.
- ▶ JpegStreamReader - IP Cameras
  - ▶ Give it a url to camera's web feed, and scrape images.
  - ▶ Getting the URL straight can be tricky.
- ▶ Virtual Camera
  - ▶ A virtual camera that pulls from a directory full of images, or video.
  - ▶ Interface to video files for processing.

# Briefly: Other Cameras

- ▶ Document Scanners
  - ▶ SANE compatible devices.
  - ▶ Allow you to set resolution and ROI.
- ▶ Digital Camera
  - ▶ Uses Piggy Photo Library
  - ▶ Works with most DSLRs and point and shoots.
- ▶ AVT Camera
  - ▶ Professional digital imaging cameras with interchangeable optics.
  - ▶ Fine grain control of camera parameters.

# Image Sets

ImageSets are lists of images. They are great for aggregating datasets.


- ▶ By default load all image files in a directory.
- ▶ Can iterate over the list using list comps or for loops.
- ▶ Using the BeautifulSoup library can download sets from google.
- ▶ Can save image sets to directories, or animated gifs!
- ▶ The show command works just like on image class.
- ▶ Can apply averages to images.
- ▶ More coming soon.

# ImageSet Example

## Example (Image Sets)

```
mySet = ImageSet()
mySet.download('cats') # download cats
mySet.show() # show them to us
avgCat = mySet.average() # get the avg cat
avgCat.show() # show the avg cat
mySet[3].show() # show the third kitty
resized = mySet.standardize(128,64)
resized.save('cat.gif')
mySet.save('cat.gif') # save the cats as a gif
for cat in mySet: # iterate over the set of cats
    cat.binarize().show()
```

## Getting at a pixel



- ▶ SimpleCV treats images as two dimensional arrays of color value tuples.
- ▶ Each tuple holds three values (Red,Green,Blue).
- ▶ Pixels start in the top left corner at zero.

# Pixel Manipulation Example

## Example (Getting at those pixels)

```
img = Image('helloworld.jpg')
c = img[0,0] # get a pixel
print c
print img.getPixel(0,0) # get another way
test = img[200:300,200:300]
test.show() # the result is an image
test = img[50:,:]
test.show() # again using slice
test = img[0:5,0:5]
print test.getNumpy() # get the raw values
img[0:105,0:105] = Color.RED
img.show() # Another way
test = img.getNumpy() #RIGHT!
test[0:105,0:105] = Color.RED
img2 = Image(test)
img2.show()
```



## Getting at a pixel

- ▶ Images are read only. To write a pixel directly you need create a new image. Usually this happens in numpy
- ▶ Images support the list slice notation but return images.
- ▶ To get at the raw pixel values use **getNumpy()** and **getGrayNumpy()**
- ▶ Numpy values can be accessed using slices the first parameter is x, the second is y, and the third is the channel in RGB order. For example `npimg[x][y][0]`.
- ▶ The **Image.width** and **Image.height** member variables can help you find your way.

# Another Pixel Manipulation Example

## Example (Fancy Manipulations)

```
img = Image('helloworld.jpg')
gray = img.getGrayNumpy() # get the gray scale np image
colored = img.getNumpy() # and the colored one
print (img.width,img.height) #tell us the image size
colored[0:20,:] = Color.BLUE # set the left side to blue
colored[:,0:20] = Color.GREEN # set the top row to green
colored[40:80,40:80]          \quad
    \includegraphics[width=0.4\linewidth]{JanEricBook.jpg}
= Color.YELLOW # make a yellow square
x,y = np.where(gray>230) # find bright pixels > 230
for xf,yf in zip(x,y): # for each of those
    colored[xf][yf] = Color.RED #make them red
img2 = Image(colored) # create an image
img2.show() # and show it
# now set the whole blue channel to 255
colored[:, :,2] = 255
# and show us that
img3 = Image(colored)
img3.show()
```

# Getting at a pixel




Figure: Not bad for less than 20 lines of code.

# Cropping, Scaling, Rotating, etc

It is helpful to think of some image processing like using an image editor, like GIMP, paint, or that other one Adobe makes. Here are a few basic image operations you can do in SimpleCV.

- ▶ **Image.crop**. Does what it says on the tin. We refer to crop areas by there top left corner x and y plus the width height.
- ▶ **Image.scale** scales the image proportionally while **Image.resize** resizes the image to the desired size.
  - ▶ **Image.resize** is smart, if you tell it a width or height it will infer the other parameter from the aspect ratio.
  - ▶ **Image.scale** uses a proportionality. So passing it value of two will double the image size. Make sure to check out the interpolation method.

# Rotating

- ▶ **Image.rotate** takes an angle in degrees.
- ▶ Rotate has a parameter called `fixed`. If `fixed` is set to `false`, SimpleCV will create a new image that matches the rotated image size. Otherwise we stick the rotated image in data in a similarly sized canvas.
- ▶ It is possible to pick the `x,y` position of the rotation. The default is the center of the image.
- ▶ You can also scale an image while rotating.
- ▶ In a pinch you can use **Image.flipHorizontal** and **Image.flipVertical**.
- ▶ Be aware **FLIPPING != ROTATION**

# Blit

The **Image.blit** function gets its name from the old computer graphics term “bit block image transfer”. Really it means just copy and paste another image onto another image and return the result.

- ▶ Blit takes in another image and a position where you want to put it.
- ▶ That position can be negative with respect to the destination image. For example  $(-10, -10)$  would put the source image over the top left of the destination image.
- ▶ You can pass blit a binary mask, an alpha value (that is transparency) or an alpha mask (a grayscale image that has an alpha mask per pixel).

# Let's play!

## Example (Basic Manipulations)

```
img = Image('tricky.jpg')
face = img.crop(150,190,309-150,333-190)
img.show() # show the source
face.show() # show the cropped image
face.rotate(45).show() # basic rotation
face.rotate(45,fixed=False).show()
face.scale(0.5).show()
face.scale(width=int(face.width/2.0)) # basic scaling
face.flipHorizontal().show() # flipping
test1 = img.blit(face.flipHorizontal(),pos=(150,190))
test1.show() # now let's have fun with blitting
test2 = img.blit(face.flipHorizontal(),pos=(150,190),alpha=0.5)
test2.show()
mask = Image((face.width,face.height))
# Here we are just drawing a white circle on a black background
mask.drawCircle((face.width/2,face.height/2),70,color=Color.WHITE, thickness=-1)
mask = mask.applyLayers()
mask.show()
test3 = img.blit(face.flipHorizontal(),pos=(150,190),mask=mask)
test3.show()
face.binarize().blur().show()
test4 = img.blit(face.flipHorizontal(),pos=(150,190),alphaMask=face.binarize().blur())
test4.show()
```

# The Blit Progression of President Dick Nixon




Figure: Various blitting

Can you our subject a smaller face or a slightly slanted face?



## A few more basics




- ▶ **Image.blur** - A basic Gaussian blur.
- ▶ **Image.smooth** - A variety of smoothing filters. Some good for removing camera noise.
- ▶ **Image.toGray** - Convert a color image to a gray scale image.
- ▶ **Image.threshold** - Take an image and set all off the pixels that have a grayscale value above the threshold to white, and everything else to black.
- ▶ **Image.invert** - Swap the lightest and darkest values, like a photo negative.

# Let's Talk about color, color spaces, and much more.




Computer vision is all about moving from a vast amount of information to small result as quickly as possible. Working in grayscale, or black and white images can speed things up dramatically.

# Color is surprisingly hard to represent



We start with visible light, which bounces around, does funky stuff, and then enters our eye or camera. Our eyes and cameras have a response function that does an imperfect job of sampling the parts of the spectrum. We then take those samples and try to map them onto finite color space like RGB.

# An illustration of why color is hard.




Point to where this magenta flower lives on the visible light spectrum.

# MIND BLOWN!



Magenta doesn't exist in nature. It tricks our brains and cameras play on us. It exists because we sample the spectrum and try to recombine the samples. We wrap the visible spectrum around.

To manage this problem we use color spaces.



- ▶ To deal with this problem we use color spaces.
- ▶ Most images are in the RGB, BGR, or gray scale color spaces.
- ▶ Sometimes it is helpful to use the hue, saturation, and value (HSV) color space. In HSV you have a
  - ▶ Hue, or pure color (from 0 to 180)
  - ▶ Saturation that tells us how far from white our color is
  - ▶ Value that tells us how dark the color is.

# How do I work with Color in SimpleCV

- ▶ The **Image.toHSV()** function will convert your image, while the **Image.toBGR()** function will return it back to the original.
- ▶ We also have **Image.toGray()** and **Image.toRGB()** and whole bunch more.
- ▶ The **Image.huePeaks** function can help you guess what hues are in your image.
- ▶ The **Image.hueDistance** function can then help you look for stuff that is the hue you want.
- ▶ The **Image.hueHistogram** function will let you visualize the results.

# Finding colors

## Example (Using Hue)

```
import pylab as plt # import pylab for plotting
img = Image("flower.jpg")
img.show()
peaks = img.huePeaks() # find the hues
print peaks
hist = img.hueHistogram() # get the histogram too
plt.plot(hist) # plot the histogram
plt.draw() # show it to us
# show how far away from the hue we are black is closer
# white is farther away from our hue.
hdist = img.hueDistance(peaks[3][0])
# create a black and white version of our flower
binary = img.hueDistance(peaks[3][0]).invert().threshold(220)
hdist.show()
binary.show()
hdist.save('hflower.png')
binary.save('bflower.png')
```



# Color Finding Results




Figure: Finding an object from colors

## How do I work **without** Color in SimpleCV

Color is not so important when all we care about are light or dark things.

- ▶ We can use the **Image.toGray** method to create gray images. Gray pixels only go from values of 0 to 255
- ▶ Sometimes it is helpful to adjust the contrast for us to find objects.
  - ▶ If the gray values in our image only go from say [50,150] we can use the **Image.equalize** method to interpolate them to values between [0,255].
  - ▶ Other times we want to enhance a certain space of the gray spectrum. We can use the **Image.stretch** function.
- ▶ **Image.histogram** can help us figure out what gray values are present.
- ▶ **Image.maxVal** and **Image.minVal** can help us determine the range of intensities and where to set our thresholds.

# Shades of Gray

## Example (Modify Grayscale Images)

```
img = Image('penguins.jpg')
img = img.toGray()
eImg = img.crop(180,400,100,100)
img.drawRectangle(180,400,100,100)
plt.plot(eImg.histogram(), '-r')
plt.plot(eImg.equalize().histogram(), '-b')
plt.show()
img.show()
eImg.show()
eImg.equalize().show()
max = eImg.maxValue()
min = eImg.minValue()
print [max, min]
stretched = img.stretch(min,max)
stretched.show()
```

# Seeing in Black and White - Binary Images

Very often we want to just isolate a certain area in an image and mark it. To do this we use binary images, also called masks. The general process of creating a binary image is called segmentation. Often we call the white areas foreground and the black areas background.

- ▶ We can use the **Image.threshold** method to create a binary image.
  - ▶ Threshold will set gray values below the threshold to black and areas above the threshold to white.
  - ▶ SimpleCV will automatically convert color images to grayscale images for a threshold.
- ▶ The **Image.binarize** method will also create a binary image.
  - ▶ Binarize uses Otsu's method which changes the threshold automatically to improve performance.
  - ▶ There are a lot of parameters to tweak so checkout the documentation.

# Basic Binarization

## Example (Let's find the parrot)

```
img = Image('parrot.jpg')
b = img.binarize().invert() # automatic
t1 = img.threshold(50) # too low
t2 = img.threshold(128) # okay
t3 = img.threshold(200) # too high
b.show()
t1.show()
t2.show()
t3.show()
b.save('bparrot.png')
t1.save('t1parrot.png')
t2.save('t2parrot.png')
t3.save('t3parrot.png')
```

## Binzarization Results



Left to right, source image, binarize using Otsu's method,  
threshold = 50, threshold=128, threshold=200

# Morphological Operations - Fixing Binarized Images




Figure: Source image, source after erosion, source after dilation.

We can clean up binary images using basic morphology operations.

- ▶ We can use the **Image.dilate** to enlarges our white areas and connects them.
  - ▶ Basically if a pixel touches a white pixel we set it to white.
  - ▶ Can be used repeatedly. Works in color too.
- ▶ The **Image.erode** method shrinks our white areas image.
  - ▶ If a white pixel touches a black pixel we set it to black.
  - ▶ Can be used repeatedly.
- ▶ **Image.morphOpen** and **Image.morphClose** do similar things but are used to open and close regions.

# Fixing Binarized Images II

There are other techniques we can use to fix things.

- ▶ **Image.floodFill** works just like the paint bucket tool in an image editor. It can get rid of areas.
- ▶ **Image.watershed** is a sophisticated technique that can really help.
- ▶ We can also logically and, or, xor, and nand images.
  - ▶ Logical and is just multiplication or **Image.logicalAND**
  - ▶ Logical or is just multiplication or **Image.logicalOR**
  - ▶ Logical xor is **Image.logicalXOR**
  - ▶ Logical nand is **Image.logicalNAND**
  - ▶ These all work in color and gray scale too.




# Advanced Binarization

## Example (Get a binary representation of the parrot.)

```
img = Image('parrot.jpg')
img.show()
binary = img.binarize().invert() # automatic
binary.show() # good but we're missing part of the beak
binary2 = img.hueDistance(80).invert().threshold(190)
binary2.show() # missing a different part of the beak
filled = binary.floodFill((0,img.height-1),color=Color.BLACK)
filled.show() # get rid of the branch in the corner
better = filled.logicalOR(binary2)
better.show() # combine the two.
eroded = better.erode()
eroded.show() # get rid of specs.
dilated = better.dilate()
dilated.show() # get rid of holes
watershed = img.watershed(dilated)
watershed.show() # let's see what this can do
```

# Parrot Pipeline



Or pipeline, left to right, top to bottom

# Finding Stuff



Now that we've got a lot of the basics down let's start doing stuff with images. Let's **find** interesting sets of **features** in our images.

## Finding Stuff II

SimpleCV allows you to quickly and easily find **features** in your images using a variety of methods that begin with the word **find**.

**Features** have a set of basic properties that makes manipulating them super easy.

The **Image.findXXXX** methods each return a **FeatureSet** which is a list of features.

A **FeatureSet** also allows you to look at aggregate information about features.

# Things you can find in SimpleCV

- ▶ Blobs - binary objects
- ▶ Lines
- ▶ Corners
- ▶ Circles
- ▶ Haar Features
  - ▶ faces
  - ▶ eyes
  - ▶ mouths
  - ▶ much more.
- ▶ Barcodes
- ▶ Text
- ▶ Templates (example images)
- ▶ Keypoints (interesting areas)
- ▶ Keypoint Matches
- ▶ Motion (between images)
- ▶ Skintone Blobs

# The Basic Mechanics

Once you have a **FeatureSet** you can use iteration either in a loop or using python list comprehensions to filter your features to get what you want.

- ▶ **Feature.draw** Will draw the feature on the source image.
- ▶ **Feature.show** Will show the feature on the source image.
- ▶ **Feature.crop** Will return an image of just the feature.
- ▶ **Feature.meanColor** Will return the average color.
- ▶ The feature's width, height, and position can also be checked.

# The Basic Mechanics II

- ▶ **Feature.area** gives the area of the feature.
- ▶ **FeatureSet.filter** Allows you to filter features on different criteria.
- ▶ **FeatureSet.distanceFrom** will return the distance of each feature from a point.
- ▶ **FeatureSet.area** returns the area of every feature as a list. By default we sort the feature set from smallest to largest.
- ▶ FeaturesSets also know the center points of the features and their corners.

# Finding Blobs

**Blob** is a backronym for binary large object. They are basically anything that would be white in a binary image. You can find blobs in a variety of ways:

- ▶ **Image.findBlobs** will do a binarize and return the blobs it found.
- ▶ **Image.findBlobs** will use a binary image, also called a masks, to find blobs.
- ▶ **Image.findBlobsFromPalette** will find blobs with specific colors from a palette
- ▶ **Image.findBlobsFromWatershed** will find blobs using the watershed algorithm and a binary image you provide



Let's see an example.






Can we write some python to find the star cookie in the top right corner?

# Sorting blobs

## Example (Finding the yellow cookie in the corner.)

```
img = Image('cookies.jpg')
# find our cookies and draw them red, filled in
blobs = img.findBlobs(threshval=128, minsize=200)
blobs.draw(width=-1, color=Color.RED) #autocolor= True)
# find the mean and std blob areas
areaAvg = np.mean(blobs.area())
areaStd = np.std(blobs.area())
# filter the cookies by area and draw those green
lilcookies = blobs.filter(blobs.area() < areaAvg+2.5*areaStd )
lilcookies.draw(width=-1,color=Color.GREEN)
# Now sort the cookies so the yellow ones are at 0
lilcookies = lilcookies.sortColorDistance(color=Color.YELLOW)
lilcookies[0:4].draw(width=-1,color=Color.YELLOW)
# Now take our yellow cookies and see how
# far they are away from the top right corner
dists = lilcookies[0:4].distanceFrom((img.width,0))
# find the closest one to the corner
location = np.where(dists==np.min(dists))[0][0]
lilcookies[location].crop().show()
lilcookies[location].draw(width=-1,color=Color.HOTPINK)
img.show()
```

# Cookie Sorting



## Paragraphs of Text

Sed iaculis dapibus gravida. Morbi sed tortor erat, nec interdum arcu. Sed id lorem lectus. Quisque viverra augue id sem ornare non aliquam nibh tristique. Aenean in ligula nisl. Nulla sed tellus ipsum. Donec vestibulum ligula non lorem vulputate fermentum accumsan neque mollis.

Sed diam enim, sagittis nec condimentum sit amet, ullamcorper sit amet libero. Aliquam vel dui orci, a porta odio. Nullam id suscipit ipsum. Aenean lobortis commodo seDerkt commodo leo gravida vitae. Pellentesque vehicula ante iaculis arcu pretium rutrum eget sit amet purus. Integer ornare nulla quis neque ultrices lobortis. Vestibulum ultrices tincidunt libero, quis commodo erat ullamcorper id.

# Bullet Points

- ▶ Lorem ipsum dolor sit amet, consectetur adipiscing elit
- ▶ Aliquam blandit faucibus nisi, sit amet dapibus enim tempus eu
- ▶ Nulla commodo, erat quis gravida posuere, elit lacus lobortis est, quis porttitor odio mauris at libero
- ▶ Nam cursus est eget velit posuere pellentesque
- ▶ Vestibulum faucibus velit a augue condimentum quis convallis nulla gravida

# Multiple Columns

## Heading

1. Statement
2. Explanation
3. Example

Lorem ipsum dolor sit amet, consectetur adipiscing elit. Integer lectus nisl, ultricies in feugiat rutrum, porttitor sit amet augue. Aliquam ut tortor mauris. Sed volutpat ante purus, quis accumsan dolor.

# Table

Treatments	Response 1	Response 2
Treatment 1	0.0003262	0.562
Treatment 2	0.0015681	0.910
Treatment 3	0.0009271	0.296

Table: Table caption

# Theorem

Theorem (Mass–energy equivalence)

$$E = mc^2$$



# Verbatim

## Example (Theorem Slide Code)

```
def doStuff(a,b,c=[1,2,3]):  
    a = 5  
    b = a  
    c.reverse()  
  
derp = [1,2,3,4]  
for i in derp:  
    doStuff()  
    pass  
print derp
```

# Verbatim

## Example (Theorem Slide Code)

$E = mc^2$

# Figure

Uncomment the code on this slide to include your own image from the same directory as the template .TeX file.

# Citation

An example of the `\cite` command to cite within the presentation:

This statement requires citation [?].

# References



John Smith (2012)

Title of the publication

*Journal Name* 12(3), 45 – 678.

# The End